West Coast Pale Ale

Recipe designed for a full (5 gallon) boil.

If doing a partial boil, boil approximately half of the malt extract/fermentables for the full 60 minutes. Add the rest with 10 minutes remaining. This will ensure proper hop utilization.

Yeast Starter:

When using liquid yeast, a yeast starter is recommeded for ales above OG 1.050, and all lagers.

Ingredients / Brew Schedule:

If you need detailed brewing instructions, please refer to the Resources/HowTo section at RiteBrew.com

.25lb Caramel 20L 6lb Gold DME 1oz Northern Brewer hops 1oz Centennial hops 2oz Cascade hops 2oz Glacier hops 1oz Crystal hops 1oz Ahtanum hops Ale Yeast Steep 20 Minutes at 155F 60 minute boil 60 minute boil 5 minute boil Dry hop 5-7 days Dry hop 5-7 days Dry hop 5-7 days Dry hop 5-7 days Ferment at 64-68F

Additional Notes:

Cold-crashing to drop the yeast before dry-hopping will help extract maximum hop aroma.

Priming/Carbonating:

Bottle Caps and Priming sugar not included. This beer should have Medium carbonation (2.3-2.7 volumes of CO2).

Weight Measurements: 4.5oz corn sugar, or 4.3oz table sugar.

Volume Measurements: 1 cup Corn Sugar (loose, fluffed), 3/4 cup Corn Sugar (packed), or 1/4+1/3 cup table sugar.

Make sure fermentation is complete before bottling!

Hydrometer reading should be remain steady for a MINIMUM of three days.

Typical Analysis:

OG: 1.051 Color: 8 SRM IBU: 38 - ABV: 5.1%

Packed On: 12/9/2020

